


TradePanel — User Guide

Standalone MT4 Trade Manager Indicator



TradePanel on a BTC/USD H1 chart

Setup

Add the latest version of **TradePanel** as an indicator to any chart — no EA required. Works independently on any symbol. Add it to multiple charts to manage trades on different symbols simultaneously.

Note: If rows appear cut off, increase **TM_PanelHeight** to 270 in the indicator inputs.

Moving & Hiding the Panel

To drag: Click and drag the ":: TM ::" label anywhere on the chart.

To hide/show: Click the **TM** button. Green = visible, Red = hidden. The TM button and drag handle stay visible when hidden.

Info Line

Top row shows live open trade count and total P&L for the current symbol, updating every 500ms. Green = profit, Red = loss, Yellow = flat.

Button Reference

Button	Function
Take Profit / SET	Enter a price, click SET. Applies that exact TP price to all open positions on the symbol.
Change SL (pts/pips) / SET	Enter a distance, click SET. Moves SL to current price \pm N pts (indices) or N pips (forex) on all open positions.

Trail Stop (pts/pips) / ON/OFF	Enter a distance or use the 5/10/15/20 presets, click OFF to activate. Trailing stop follows price every 500ms — only moves SL in the favourable direction, only once trade is beyond entry. Click ON to deactivate.
5 / 10 / 15 / 20	Preset trail distances. Sets the value only — click ON separately to enable. For indices these are points; for forex these are pips.
EXT SL	Extend Stop Loss N pts/pips further from entry. Toggle ON applies immediately. Use +/- to adjust N while ON to reapply instantly. Sets SL from entry price (not current price).
EXT TP	Extend Take Profit N pts/pips further from entry. Only applies if a TP is already set. Toggle and +/- work the same as EXT SL.
CL — Close All	Closes all open market orders (BUY/SELL) on the current symbol. Pending orders (limit/stop) are not closed.
BE — Breakeven	Moves SL to entry + small offset on all profitable positions. Only triggers if profit >= TM_BreakEvenTrigger (default 5). Skips trades where SL is already better than BE level.
REV — Reverse	Calculates net position, closes everything, then opens the opposite direction at the same lot size. Executes immediately — use with care.

Key Difference: EXT SL vs Change SL

Change SL (pts/pips) — Sets SL relative to the *current price*. Use when you want to define risk from where price is right now.

EXT SL — Sets SL relative to the *entry price*. Use when you want to give a trade more room from its original entry point.

Instrument-Specific Settings

The panel auto-detects whether to use **points** (indices) or **pips** (forex) based on the symbol's Digits and price level:

- **Indices (US30, NASDAQ, BTC):** Close > 1000 → 1 unit = 1 point
- **Forex 5-digit (EURUSD, GBPUSD):** Digits = 5 → 1 unit = 1 pip (auto-normalised)
- **Forex 3-digit (USDJPY):** Digits = 3 → 1 unit = 1 pip (auto-normalised)

Recommended input values per instrument:

Input	US30 (DOW)	NASDAQ	BTC/USD	Forex (EURUSD)
DollarsPerPoint	\$3/pt	\$2/pt	\$1/pt	\$10/pip (1 std lot)
BreakEvenTrigger	5 pts	5 pts	50 pts	10 pips
BreakEvenOffset	1 pt	1 pt	5 pts	1 pip
Trail distance	10 pts	10 pts	100 pts	20 pips

EXT SL default	10 pts	10 pts	100 pts	15 pips
EXT TP default	15 pts	15 pts	150 pts	20 pips

Tip: Save a separate MT4 indicator profile for each instrument with these inputs pre-configured, then load the profile when switching markets.

Configurable Inputs

Input	Default	Description
TM_Window	0	Chart window (0=main chart)
TM_PanelX	250	X position from left edge (pixels)
TM_PanelY	30	Y position from top (pixels)
TM_PanelWidth	400	Panel width in pixels
TM_PanelHeight	270	Panel height in pixels
TM_Font	Impact	Font for all panel text
TM_FontSize	13	Font size
TM_BreakEvenTrigger	5.0	Min profit in pts/pips before BE activates
TM_BreakEvenOffset	1.0	Pts/pips above/below entry for BE stop loss
DollarsPerPoint	3.0	Dollar value per point/pip — used for P&L display